# **Heading 2: LAN & DHCP Setup**

# Topic 2.1 - Assigning LAN IP to Bridge/LAN Interface

Step 1: Assign IP to LAN (Bridge or Single Interface)

CLI:

/ip address add address=192.168.10.1/24 interface=bridge1

(If not using a bridge, assign to ether2 directly)

/ip address add address=192.168.10.1/24 interface=ether2

# Winbox:

- Go to IP  $\rightarrow$  Addresses  $\rightarrow$  Add (+)
- Address: 192.168.10.1/24
- Interface: LAN\_Bridge (or ether2)




Image - Assign IP to LAN (Bridge or Single Interface)

# Topic 2.2 - Configure DHCP Server for LAN

# Step 1: Create IP Pool

CLI:

/ip pool add name=LAN-Pool ranges=192.168.10.10-192.168.10.254

#### Winbox:

• Go to IP  $\rightarrow$  Pool  $\rightarrow$  Add (+)

• Name: LAN-Pool

• Range: 192.168.10.10-192.168.10.254




Image - Create IP Pool

# Step 2: Configure DHCP Network

CLI:

/ip dhcp-server network add address=192.168.10.0/24 gateway=192.168.10.1 dns-server=8.8.8.8,1.1.1.1

#### Winbox:

• Go to IP  $\rightarrow$  DHCP Server  $\rightarrow$  Networks  $\rightarrow$  Add (+)

• Address: 192.168.10.0/24

• Gateway: 192.168.10.1

• DNS Servers: 8.8.8.8,1.1.1.1




Image - Configure DHCP Network

# Step 3: Add and Enable DHCP Server

#### CLI:

/ip dhcp-server add name=LAN-DHCP interface=bridge1 address-pool=LAN-Pool disabled=no

(If not using bridge, use interface=ether2)

## Winbox:

- Go to IP  $\rightarrow$  DHCP Server  $\rightarrow$  DHCP Setup
- Select Interface: bridge1 (or ether2)
- Set Pool, Gateway, and DNS as prompted




Image: Add DHCP Server




Image: DHCP Setup 1




Image: DHCP Setup 2




Image: DHCP Setup 3


Topic 2.3 - Test LAN Connectivity

CLI:

/ping 8.8.8.8

## Winbox:

- Go to Tools  $\rightarrow$  Ping
- Enter 8.8.8.8



**Image: Test Connectivity** 

If successful, LAN clients should have automatic IP via DHCP and Internet access via NAT.